

ElecRoc MAC log on problem

Cannot connect to server:

- 1 logon Mac with administrator user, this user should have password
- 2 run terminal
- 3 type cd /
- 4 type cd etc
- 5 type sudo vi hosts
- 6 input password---attention, when input pw, nothing happen in window, donot care about that, just finish input and return
- 7 there appear host database window
- 8 type i to enable input in this window
- 9 move input symbol under ::1 localhost
- 10 type ipaddress of Pc, space, Pc computer name---attention, the format should be same as upper
- 11 click esc
- 12 type :wq to save and quit
- 13 quit terminal
- 14 ping Pc with computer name
- 15 if it is Ok, please go to system

preference>network>ethernet>advanced>proxies, deselect web proxy

16 run ElecRoc client and logon with computer name

No authorized

- 17 run terminal
- 18 type uname –n
- 19 type sudo hostname XXX
- 20 type uname –n, you can get the computer name
- 21 input Mac name.**local** into ElecRoc Server\Settings\ Author Control

BTW, ElecRoc v5 supports Java v1.5 and above. Please check it by Run java-version on Mac client.

How to find out your Mac's name?

1. To see your current computer name, Local Hostname, or network address, open the Sharing pane of System Preferences.
2. Check the option of File Sharing, the name is listed under File Sharing: On