

## **ElecRoc MAC log on problem**

### **Cannot connect to server:**

- 1 logon Mac with administrator user, this user should have password
- 2 run terminal
- 3 type cd /
- 4 type cd etc
- 5 type sudo vi hosts
- 6 input password---attention, when input pw, nothing happen in window, donot care about that, just finish input and return
- 7 there appear host database window
- 8 type i to enable input in this window
- 9 move input symbol under ::1 localhost
- 10 type ipaddress of Pc, space, Pc computer name---attention, the format should be same as upper
- 11 click esc
- 12 type :wq to save and quit
- 13 quit terminal
- 14 ping Pc with computer name

**Beijing Founder Electronics Co., Ltd.**

No. 9, 5th Street, Shangdi Information Industry Base  
Haidian District, Beijing 100085, People's Republic of China  
Tel: +86 10 62981440 Fax: +86 10 62981440  
[www.founder.com.cn](http://www.founder.com.cn)

15 if it is Ok, please go to system

preference>network>ethernet>advanced>proxies, deselect web proxy

16 run ElecRoc client and logon with computer name

### **No authorized**

17 run terminal

18 type uname -n

19 type sudo hostname XXX

20 type uname -n, you can get the computer name

21 input Mac name.**local** into ElecRoc Server\Settings\ Author Control

### **Beijing Founder Electronics Co., Ltd.**

No. 9, 5th Street, Shangdi Information Industry Base  
Haidian District, Beijing 100085, People's Republic of China  
Tel: +86 10 62981440 Fax: +86 10 62981440  
[www.founder.com.cn](http://www.founder.com.cn)