# How to upgrade ElecRoc 5 dongle on Windows 2008

When you add modules or functions for ElecRoc 5 dongle, please be sure that you've got a license key (\*.pkg) from your sales man.

### Warning:

1, Only when you need to install the NEW modules, can you run Processor. Configuration. Otherwise, if the Processor Configuration appears, as following, you MUST click 🗵 to exit.



2, Exit ElecRoc 5 at first.

3, Be sure the dongle driver was installed on this ElecRoc 5 Server computer, and the dongle was plugged in this computer before running License Manager.

4, DO NOT UNPLUG the dongle from computer, and keep the POWER ON while this tool is working. Otherwise, the dongle has risk of be damaged.

If you have already known the previous important information, you can continue to add modules or functions to your dongle.

STEP 1:

Start License Manager from Start\All Programs\Founder ElecRoc\Configuration Tools\, then click Query button, show as following:

Query(Q)
Browse( <u>B</u> )
Update(U)
histool

### STEP 2:

When Dongle ID, Device ID shows up, click Browse to find out the license key (\*.pkg)

cense Manager		
Dongle ID:	699500001	Query(Q)
Device ID:	95 19 97 00 00 00 40 6d	
License Key(*.pkg):	\\ibdsr\\PM&Marketing\ElecRoc-Bon\Testing files\PKG\6995	Browse( <u>B</u> )
WARNING: 1. Quit ElecRoc 5 Serve	er and Client before running this tool.	Update( <u>U</u> )
installed.	d on the ElecRoc 5 Server computer with the dongle driver	
<ol> <li>This tool is only used installed.</li> <li>DO NOT UNPLUG this working. Otherwise, the</li> </ol>	d on the ElecRoc 5 Server computer with the dongle driver ne dongle from computer and keep the POWER ON while this tool he dongle has risk of be damaged.	

# STEP 3:

Click Update button, a window shows up, as following:

ElecRocMOD			
– Module id: 6a			Install( <u>i</u> )
- Version: 5.0.0.0	0 0		
Include EF file nu	imber:1		Close( <u>C</u> )
ackage information-			
ackage information-	Specific user	For specific user:	95 19 97 00 00 00 40 6d
ackage information – Jpdate scope: vlodule update type:	Specific user Update existing module	For specific user:	95 19 97 00 00 00 40 6d
ackage information- Jpdate scope: Vodule update type: Valut typo:	Specific user Update existing module	For specific user:	95 19 97 00 00 00 40 6d
ackage information – Jpdate scope: Vodule update type: /alid type:	Specific user Update existing module Valid permanently	For specific user:	95 19 97 00 00 00 40 6d

## STEP 4:

Click Install, an information appears, to continue click Yes, to exit click No.

odule information in pa	ackage		
ElecRocMOD			Install())
-Version: 5.0.0.0	1001 T 1000 - 4		
™ Include EF file nu	imber:1		Close( <u>C</u> )
Important In	formation date will stop ElecRoc. If you u s process will change the modu	nplug the dongle or the power is les or functions in the dongle, an	off, maybe the dongle will be distorted. e you sure to continue?
Important In Lup Th Package information -	formation date will stop ElecRoc. If you u s process will change the modu	nplug the dongle or the power is les or functions in the dongle, an <u>Yes</u> <u>No</u>	off, maybe the dongle will be distorted. e you sure to continue?
Important In Up Package information – Update scope:	formation date will stop ElecRoc. If you u s process will change the modu Specific user	nplug the dongle or the power is les or functions in the dongle, an <u>Yes</u> <u>No</u> For specific user:	off, maybe the dongle will be distorted. e you sure to continue? 95 19 97 00 00 00 40 6d
Important In Up Th Package information – Update scope: Module update type:	formation date will stop ElecRoc. If you u s process will change the modu Specific user Update existing module	nplug the dongle or the power is les or functions in the dongle, and <u>Yes</u> <u>No</u> For specific user:	off, maybe the dongle will be distorted. e you sure to continue? 95 19 97 00 00 00 40 6d
Important In Package information – Update scope: Module update type: Valid type:	formation date will stop ElecRoc. If you u s process will change the modu Specific user Update existing module Valid permanently	nplug the dongle or the power is les or functions in the dongle, an <u>Yes</u> <u>No</u> For specific user: Major Version:	off, maybe the dongle will be distorted. e you sure to continue? 95 19 97 00 00 00 40 6d

STEP 5:

If click Yes on step 4, the Update Result window will pop up, as following, to show the update is successful. And please click OK, then click Close button.



STEP 6:

Run RestartService.vbs from installer DVD\Tools\Restart Dongle Service; or start Elite4 Net Service from Computer Management\Services and Applications\Services by manually. And then run Processor Configuration from Start\All Programs\Founder ElecRoc\Configuration Tools.

STEP 7:

When Processor Configuration appears, it shows the dongle update is successful. And next you need to configure the modules you have bought. Click Next to continue.

Processor licensed by	Configuration	is a tool	to configur	e the module er Name/IP o	es which
5 Server a	nd the Name/I	IP of Compu	iter where the	e dongle is plu	gged.
Default is f	the name of th	nis compute	r.		
Computer	Name or IP of	ElecRoc 5	Server		
Name/IP:	2003V5				
Computer	Name or IP of	ElecRoc 5 (	Dongle		
Name/IP:	2003V5				
If you use Click Apply	the default i	name, Click	Next, If you	change one	of them,

### STEP 8:

Click Unselect All on the following window.



STEP 9:

After clicking Unselect All, the window appears as following:

Processor Configuration		×
∧ Input	Select All	ſ
PDF Generator		71
∧ Composer	Unselect All	
Imposer	Next	Ê
🗖 Auto Composer		
PDF Processing		
🗖 Double Burn		
PDF Tools		
🗖 Тгар		
🗖 EcoInk		
^ Output		
🔲 Ink Control Export		
1 Bit TIFF Export	. Evit	Ê.
Mono Printer	<u> </u>	

If you purchased the licenses such as EagleFM, EagleFAM, zone trap, Imposer + (Type C), load balancing license, etc. All of them are not show on this window, but have been configured in the ElecRoc 5, so please click 🗵 to exit.

If the modules you purchased show on this window, please select them only. Don't select the modules which are not your purchasing, otherwise ElecRoc 5 has some problem. For example, you only purchased the modules of Trap, EcoInk and Ink Control Export (CIP3), please select as following.

STEP 10:

Select the modules which you purchased only, and then click Next button.

Processor Configuration	
^ Input	Select All
PDF Generator	
∧ Composer	Unselect All
Imposer	Next
🗖 Auto Composer	
∧ PDF Processing	
🗖 Double Burn	
DF Tools	
🔽 Trap	
F EcoInk	
^ Output	
Ink Control Export	
1 Bit TIFF Export	Exit
Mono Printer	

## STEP 11:

Click Install button until the installation has finished.

🚮 Trap				
Processor N	lame:			
Trap				
	Exit	Back	Skip	Install

If the error appears as following, please click OK, and then click Skip, do not install this module.

PDF Export	
Processor Name:	
PDF Export	
Error	×
The same name (PDF Export) processor has existed already, pl	ease enter another name.
Exit Back Skip	Install

End